ProModel & MedModel Lesser-Known Powerful Items

November 24, 2020 Ken Davis Sr. Consultant ProModel Corporation KDavis@ProModel.com



Items to be covered

- Techniques
- Tools
- Simulation Options
- Commands
- Support
- Functions
- Features



Caveats

 We encourage using the <u>Help system</u> and the <u>User Guide</u> for further description and clarification of these items

C:\Program Files (x86)\ProModel Corporation\ProModel\10.4\Docs\User\<u>ProModel User Guide.pdf</u> <u>Ref...</u>

- This will be rapid...
 Encourage revisiting the Recorded MP4 of this session in the ProModel website **Solutions Café** <u>Webinars</u> section
- Level of detail in discussion of each item will vary



Techniques

- You can have multiple models open and/or running at the same time
 - e.g. While the model is running (maybe being DEBUGged), make a .MOD COPY... Open & examine
- Import Background Graphic to Scale
 - BMP, WMF, JPG, GIF, PNG, TIF, ICO, PCX
 - ACAD DWG
- Array Import Worksheet name by Macro
- Array Database Import Connection String & Query
 - <u>https://www.connectionstrings.com/</u>
- Merge (but Model Collaborator may be better!!)
 - Model
 - Submodel
- Model instructions RTF
- Model Notes
- Customize Quick Access Toolbar
- Streams (1-100)
- Comment portions of a logic line
 - e.g. IF OBJECTID() = 17 THEN { **/*DEBUG*/** TRACE STEP }



Example



Tools

- Multiview Runner
- Dynamic plot
- Model Collaborator
- 3D Animator



Sim Options

- Output Reporting
 - <u>Standard</u> reporting
 - <u>Batch Mean</u> reporting
 - No Reps, Warm-up only once; Good for models with really long run times (e.g. years)
 - <u>Ref...</u> p 52 , 375
 - <u>Periodic</u> reporting
 - ... Throughout the day, week, etc.
 - <u>Ref...</u> p376
- Clock Precision Runtime speed & duration
 - <u>Ref...</u> p66
- Generate Animation Script for 3D Animator
- Common Random Numbers
 - <u>Ref...</u> p374



File-Options

- Logic Window Font specification PROMOD.INI
 - <u>C:\Users\kdavis\AppData\Local\ProModel\ProModel\10.4\PROMOD.INI</u>
 - DigitFont On-screen numbers ... Variables, LOC Contents
 - LogicFont Logic window text... Operations, Move Logic, Subroutines
 - TableFont e.g. Entities & Locations specificatio
 - TextFont e.g. LOC Aa text, Text boxes
- Autosave Interval
- Confirm Record Deletion

Models: C:\Users\kdavis\Documents\ProModel\Models Graphics C:\Users\kdavis\Documents\ProModel\Graphics Output Results: C:\Users\kdavis\Documents\ProModel\Output	Browse
	Browse
Output Results: C:\Users\kdavis\Documents\ProModel\Output	
	Browse
Auto-Save: C:\Users\kdavis\Documents\ProModel\Models	Browse
Default File	
Graphics C:\Program Files (x86)\ProModel Corporation\ProModel\10.4\C	Browse
Auto-Save Interval Confirm record deletion	
Logic Windows	



Commands

- Break Jump out of Loop
 - (While Do, Do While, Do Until)
 - Exits the innermost logic
 - <u>Ref...</u> p445
- Breakblk Abandon remainder of logic
 - Exits from the innermost statement block
 - <u>Ref...</u> p446



Support

- Solutions Café Webinars
 - <u>https://promodel.com/solutionscafe/webinars/</u>
- Solutions Café Knowledge Base
 - <u>https://promodel.com/solutionscafe/resourcelibrary/knowledgebase.asp</u>
- What's New Release Notes
 - <u>https://promodel.com/products/ProModel#Whats-New</u>



Functions

- SysClock
- ScenarioName
- ObjectId
- GetReplicationNum
- PercentOp
- PercentUtil
- LocState
 - <u>Ref...</u> p507
- DistanceTraveled

- DownQty
- FreeCap
- Units
- FreeUnits
- TimeEntered
- TimesUsed
- ResQty
- OwnedResourceUnit



Features

- Entity Spot resized regardless of zoom factor
- Highlight Logic text item... F12





Questions ??

Ken Davis KDavis@ProModel.com

